


GstarCAD server license offline activation, legacy 2013 - 2019

1007 GstarCAD Malaysia July 6, 2021 [Activate / Deactivate](#) 0 7308

Instruction: if your computer can not connect to the internet, you could use another one with internet connection help you to finish activation.

After the installation is finished, a utility program group called “GstarCAD Network License Manager)” is added to Windows Programs in which you will find:




GstarCAD License Manager (server) : Managing the list of licenses on the server computer.

LMTools : A tool which is used to manage license server for network.


Uninstall : Uninstall program

Click “GstarCAD License Manager (server)” from Windows Start button> All Programs> GstarCAD Network License Manager.



Then the following window will pop up. Click the “Activation” button.

Click “click here” to open the manual Activation guide.

The image shows a software activation window titled "Activation". It features a text input field for a serial number, a "Quantity of license" field with the value "0", and an "Activate On-line" button. Below these, it provides two activation methods: online and manual. The manual method is linked to a "click here" text, which is highlighted with a red rectangle. An "Exit" button is located at the bottom right.

Activation

Input your Serial Number

Quantity of license: 0

Activate On-line

GstarCAD provides 2 ways to activate your program:

1. If you want to activate your program on-line, please input your serial number and click "Activate On-line".
2. If your computer is not connected to the internet, please [click here](#) to use the manual activation wizard.

Exit

Follow the Activation guide. Please input Serial Number and specify the quantity of license, then click the "Generate" button to get the Application file and save it to the local computer.

Activation

Step1:

Input Serial Number which you received from your distributor to generate Application File(.xml file)

2901-DF07-0000-0100-B383-****-0000-0300

Generate

Quantity of license: 2

Step2:

There are 2 options to get the Activation File:

1. Send the Application File generated in Step 1 to your distributor by E-mail to get the Activation File.
2. [Click here](#) to go to our online activation service center to get the Activation File. Login with the serial number you have, and then use the Application File to get the Activation File.

Step3:

Input Activation File you received to activate GstarCAD


Browse...

Activate


Exit

Click Save to save the generated Application File and send the file by e-mail to your distributor from whom you purchase GstarCAD, and you will receive an Activation File correspondingly.


(e.g: 3401-DF07-0000-0100-C9D9-9801-0000-0400-resp-svr-act.xml).



After you receive the Activation File, Take the Response XML File back to your computer and continue. In the Activation dialog box, please click the “Browse” button to select the Response XML File and click the “Activate” button.



Click the "OK" button to exit.



Online URL:

<https://www.gstarcad.com.my/knowledge/article/gstarcad-server-license-offline-activation-legacy-2013-2019-1007.html>