


GstarCAD license portal self service activate

1143 GstarCAD Malaysia July 9, 2021 [Activate / Deactivate](#) 0 5349

Manual Activation

Instruction: *If your computer is not connected to the internet, you can use the activation file (XML file) to activate your GstarCAD products manually.*

1. Click **Manual Activation(M)** and select a version of GstarCAD (Professional, Standard, LT, and Education)from your computer.



GstarCAD License Manager

License Key (L)

Online Activation(O)

Manual Activation(M)

Network License(N)

Borrow License(B)

USB Dongle (D)

Product version:

Professional

Standard

Education

If there is a license of higher version existing please **ACTIVATE** it directly. For a new activation, please input license key and move to the next steps.

License key

1. **GENERATE** request file.

2. Upload request file to <https://license.gstarcad.net/> and get license file.(or send request file to your local distributor /reseller from whom you purchased GstarCAD products to get license file)


3. **LOAD** the license file and click Activate button.

Activate


Back(K)

Exit(E)

2, Input your license key (serial number)and click the **GENERATE** button to get the request file and save it.




3, There are 2 ways to acquire a license file with the saved request file:



Online Service

You can access GstarCAD online service center from any computer internet-connected to download the license file.

1. log in to [GstarCAD online service center \(license portal\):https://license.gstarcad.net/](https://license.gstarcad.net/)
2. Input your **license key** (serial number) and click the **Login** button to continue.



Please input your License to login

License

F101-E507-6D01-0100-BC2F-DAB8-0000-0300

Login

3. In the Activation tab, click the **Activate** button to continue

Activation

License Management

Device Management

My License
F101-E507-6D01-0100-BC2F-DAB8-0000-0300

Logout

Activate

My License: F101-E507-6D01-0100-BC2F-DAB8-0000-0300

Product	Encryption Type	License Type	Language	Expired	License Status	Response XML
GstarCAD Professional 2021	Stand-alone Version	Trial License	en-US+de-DE	-	Initialize	

Click "Activate" to activate your product.

4, Click the **Choose File** button and select the **request file** you have saved and click the **Submit** button to continue.

Navigation: [←](#) **Activation** | My License: F101-E507-6D01-0100-BC2F-DAB8-0000-0300 | [Logout](#)

My License: F101-E507-6D01-0100-BC2F-DAB8-0000-0300

Request XML File

Choose File

Upload File: F101-E507-6D01-0100-BC2F-DAB8-0000-0300.xml

Load the credible request XML activation file which created at user client

Submit


Find out the file and click it to submit

5. Click the **Download** button and save the license file(Response XML File). We recommend you store the license file on your USB flash drive.

Navigation: **Activation** | License Management | Device Management | My License: F101-E507-6D01-0100-BC2F-DAB8-0000-0300 | [Logout](#)


Activate

My License: F101-E507-6D01-0100-BC2F-DAB8-0000-0300


Product	Encryption Type	License Type	Language	Expired	License Status	Response XML
GstarCAD Professional 2021	Stand-alone Version	Trial License	en-US+de-DE	2020-10-20-2021-10-20	Activated	

Please download Response XML file to activate your product.
Please click "Return License" to return your license.

Back to your computer and find out GstarCAD License Manager from Help-Register in GstarCAD, please click the LOAD button and select the license file you have just downloaded and saved from another computer, and then click the Activate button.



After a few seconds, the following message window appears. Click the OK button to finish the activation. Then restart your GstarCAD.



Online URL:

<https://www.gstarcad.com.my/knowledge/article/gstarcad-license-portal-self-service-activate-1143.html>