GstarCAD Activation, Network, Software-encryption, Setting

1008 GstarCAD Malaysia June 30, 2021 <u>Installation</u> 0 5236 Server Setting

Proceed to set LMTOOLS (This utility can only be set by Administrator)

GstarCAD NetWork Licer	nse Manager
💮 GstarCAD License Ma	anager(server)
🚉 LMTools	
🐻 Uninstall	

All the information of the tabs you can keep default, you only need to operate in Start/Stop/Reread tab to manage the server.

	ode Help		
ervice/Licens	e File System Settings Utilities	Start/Stop/Reread Server Status Ser	rver Diags Config Services Borrowing
	FLEX	net license services installed on this com	puter
	Geta	(EAD	 4.
	Start Server	Stop Server	ReRead License File
		1.1.M	
		🥅 Force Server Shutdown	
	Advanced settings >>	 Force Server Shutdown NOTE: This box must be checke 	d to shut down a license server
	Advanced settings >>	Force Server Shutdown NOTE: This box must be checke when licenses are borrowed.	d to shut down a license server

You can start server either manually or automatically, it is to select Start/Stop/Reread option to control the server in Start/Stop/Reread tab or control sever automatically in Config Services tab by checking User Services and Start Server at Power Up when start the computer.

Client Setting

After the setting of server, you have connected server to user client in order to activate GstarCAD 2016 from user client machine.

After finishing the installation of GstarCAD 2016 on user client machine, start GstarCAD 2016, Welcome to GstarCAD window pops up automatically, Select a version and click Activate.

	Welcome to GstarCAD
	The trial will expire in
	30 (DAY)S
GstarCAD 2016	Please choose the version:
	Academic
	Trial Activate

A GstarCAD Register window will pop up, click Next after selecting Network Softwareencryption(Flexnet).



Specify server IP address at Server IP Address window.

Server	IP Addres	s	×
Set Se	rver IP A	ddress:	:
192.10	6 <mark>8.0.66</mark>		
Port:	27000	(2700	00-27009)
	0	к	1

Click OK button to activate GstarCAD. With this client activation method, when you close GstarCAD 2016 software ,the license will be returned to server automatically.

Online URL:

https://www.gstarcad.com.my/knowledge/article/gstarcad-activation-network-software-encryption-setting-1008.html